



IrisTM media solutions

Release Notes
Iris Anywhere / Iris Play
Version 1.7.0.23



1 Table of Contents

1	Table of Contents	1
2	GrayMeta Iris Anywhere / Iris Play	2
2.1	Version 1.2.0.5	2
2.2	Version 1.2.1.6	2
2.3	Version 1.2.2.7	2
2.4	Version 1.3.0.8	2
2.5	Version 1.3.1.9	3
2.6	Version 1.4.0.10	3
2.7	Version 1.4.1.11	5
2.8	Version 1.4.2.12	5
2.9	Version 1.4.3.13	6
2.10	Version 1.4.4.14	6
2.11	Version 1.5.0.15	6
2.12	Version 1.5.1.16	7
2.13	Version 1.5.2.17	7
2.14	Version 1.5.3.18	7
2.15	Version 1.5.4.19	7
2.16	Version 1.5.4.20	7
2.17	Version 1.6.0.22	8
2.18	Version 1.7.0.23	9

2 GrayMeta Iris Anywhere / Iris Play

2.1 Version 1.2.0.5

- 2.1.1 Initial release 15th September 2020.
- 2.1.2 This release requires Iris QC Anywhere version 8.0.0.82 or above.

2.2 Version 1.2.1.6

- 2.2.1 Optimize the Performance of displaying Position track values during Playback.
- 2.2.2 Shows calculated loudness for audio waveforms window.
- 2.2.3 Added Dolby Atmos and Dolby-e Metadata in Asset Metadata.
- 2.2.4 Fixed the Full Screen issue for Mozilla Browser.
- 2.2.5 Changed Default Video Codec from VP9 to VP8.
- 2.2.6 Added Help Option in Context menu with quick Start up Guide.
- 2.2.7 Improve the AV and Video Sync.
- 2.2.8 Fixed the timeout issue while logging in.
- 2.2.9 This release requires Iris QC Anywhere version 8.0.1.83.

2.3 Version 1.2.2.7

- 2.3.1 Fixed the Dragging Issue for mark-in and mark-out on Seek-bar.
- 2.3.2 Added SCC frame rate selector dialog when not known.
- 2.3.3 This release requires Iris QC Anywhere version 8.0.2.84.

2.4 Version 1.3.0.8

- 2.4.1 Added the “Iris Play” Product.
- 2.4.2 Fixed CSS Error for Seek Bar.
- 2.4.3 Fixed Caption’s displaying Issue.

- 2.4.4 Embedded the Version number of product at landing page.
- 2.4.5 This release requires Iris QC Anywhere version 8.0.3.85.

2.5 Version 1.3.1.9

- 2.5.1 Upgrade WRTC version for Audio Sync Issue.
- 2.5.2 Changed the Recent file option get save under the User.
- 2.5.3 Added about option in the help.
- 2.5.4 This release requires Iris QC Anywhere version 8.0.4.86.

2.6 Version 1.4.0.10

- 2.6.1 Added Timeline window and Document viewer.
- 2.6.2 Fixed bugs for Audio Mixer and Audio Routing.
- 2.6.3 Added in the option dialog a setting to enable media timebase in SRT captions.
- 2.6.4 Fixed file browser search not working in Safari.
- 2.6.5 Fixed misaligned file browser search buttons in Safari.
- 2.6.6 Support touch device for docking layout.
- 2.6.7 Display an icon in each tool window's title bar.
- 2.6.8 Added document viewer to support jump to video position by timecode / time.
- 2.6.9 Added url with hash tag to open file / asset package / image sequence folder.
- 2.6.10 Added API for opening file / asset package / image sequence folder.
- 2.6.11 In the open file manager, set the search recursive check box to 'on' by default.
- 2.6.12 Added ability to jump to timecode by manually entering it in the transport controls.
- 2.6.13 Tool windows now disabled when user is not given access to it through group permissions.
- 2.6.14 Display file loading progress during opening of files.

GrayMeta Iris Anywhere / Iris Play

- 2.6.15 When opening IMF and DCP packages, added a button to expand or collapse all CPLs.
- 2.6.16 Display detailed timeline / photon validation when opening package like DCP/IMF.
- 2.6.17 Display shortcut keys in context menu.
- 2.6.18 Added shortcut keys in options.
- 2.6.19 Fixed bug when a checkbox for an inactive mixing track was enabled but should be disabled.
- 2.6.20 Notify the user of a condition where the same user had signed out from another instance of Iris Anywhere

2.7 Version 1.4.1.11

- 2.7.1 Added support for load / save / import environment profile
- 2.7.2 Added OKTA login support
- 2.7.3 Fixed Search issue in File manager
- 2.7.4 Added Show db scale in context menu of audio phase meter
- 2.7.5 Removed Document Viewer option from IA Play
- 2.7.6 Added logging support
- 2.7.7 Fixed opening dolby vision xml and close file that breaks the connection between server and client
- 2.7.8 Added ability to open qc report file
- 2.7.9 Added Tiger Bridge support
- 2.7.10 Fixed Dolby Vision Timeline metadata appearance issue
- 2.7.11 Updated API documentation.
- 2.7.12 This release requires Iris QC Anywhere version 8.1.2.91.

2.8 Version 1.4.2.12

- 2.8.1 Update the video codec from VP8 to VP9.
- 2.8.2 This release requires Iris QC Anywhere version 8.1.2.91.

2.9 Version 1.4.3.13

- 2.9.1 Fixed bug in Options page for Captions and Subtitles where it was not possible to set a negative timecode offset.
- 2.9.2 Copy multiple files/directory using Tiger Bridge.
- 2.9.3 Fixed crash when calling openAssetPackage/openImageSequence via API.
- 2.9.4 Added Curio login.
- 2.9.5 Added Curio search tool window and to be able to import metadata from the search results.
- 2.9.6 Added Curio Speech to Text tool window.
- 2.9.7 Added Curio OCR Metadata tool window.
- 2.9.8 Added Curio Tags and Descriptions tool window.
- 2.9.9 Added Curio Timeline tool window.
- 2.9.10 Support Asset Metadata Templates for validation.
- 2.9.11 Fixed timecode entry so that the cursor is initially on the left of the timecode field and not on the right.
- 2.9.12 Fixed template creation sometimes failing.

2.10 Version 1.4.4.14

- 2.10.1 Fixed issue related to user logged out while playing file.
- 2.10.2 This Version requires the Iris QC Anywhere version 8.1.4.93.

2.11 Version 1.5.0.15

- 2.11.1 Added annotation window.
- 2.11.2 Added annotations series in timeline.
- 2.11.3 Added ability to generate QC Reports with PASS/FAIL Tag.
- 2.11.4 Added password resetting option.
- 2.11.5 Fixed error for file manager with S3 data.
- 2.11.6 Added a separate timeout setting for the current session.

GrayMeta Iris Anywhere / Iris Play

- 2.11.7 Support API authenticate through OKTA.
- 2.11.8 Added Dolby Vision stream in options and context menus.
- 2.11.9 Allow user to change update their Iris account details.
- 2.11.10 Added feature to allow user to reset password.

2.12 Version 1.5.1.16

- 2.12.1 Improved reliability of WAMP calls to resolve issues where Iris Anywhere appears to hang and do nothing.

2.13 Version 1.5.2.17

- 2.13.1 Fixed the sudden Sign out Issue while loading file.

2.14 Version 1.5.3.18

- 2.14.1 Updated Iris QC Anywhere to v8.2.4.98 with critical bug fix.

2.15 Version 1.5.4.19

- 2.15.1 Added support for Elastic search to search assets from S3 directly.
- 2.15.2 Embedded Tiger bridge ability to surf S3 files directly from bucket instead of replicating all stubs.
- 2.15.3 Asks user to specify PAC codepage for each .PAC file.
- 2.15.4 Made some Cosmetic Changes to Curio tool windows.
- 2.15.5 Added loudness Channel layouts for A85/BS1770-4 in options.
- 2.15.6 Display Dolby Atmos master metadata.
- 2.15.7 Added options for override latency samples in Dolby Atmos and display management version in Dolby vision stream.

2.16 Version 1.5.4.20

- 2.16.1 Fixed the Issue related to creation of multiple stub within folder.
- 2.16.2 This release requires Iris QC Anywhere version 8.3.0.101.

2.17 Version 1.6.0.22

- 2.17.1 Added import of Segment Data from XML.
- 2.17.2 Added annotations.xsd schema to define Segment Data XML format.
- 2.17.3 Added Segment Data Viewer.
- 2.17.4 Added Project Viewer.
- 2.17.5 Added opening, closing and deleting of projects.
- 2.17.6 Fixed jog mode and loop mode was disabled when file is not opened – it should be enabled always.
- 2.17.7 Added opening of QC Report files.
- 2.17.8 Fixed bug in Annotations Viewer whereby refreshing the browser could cause the Annotations Viewer to repeatedly select the current item and then the first item and this would continue endlessly.
- 2.17.9 Fixed a bug where setting start and end frame to be the same values in Annotations Viewer would give error message that the start frame must not be greater than end frame.
- 2.17.10 Open file API now allows a parameter to specify that a project is to be created for the file.
- 2.17.11 Added DCP/KDM Manager settings in Options.

2.18 Version 1.7.0.23

- 2.18.1 Added segment data annotations in the timeline.
- 2.18.2 Fixed bug in the file open dialog, the reset button did not reset the display to the first page.
- 2.18.3 Fixed the audio mixer that kept rendering multiple times.
- 2.18.4 Fixed annotation messages were not shown when clicking the previous and next annotation buttons.
- 2.18.5 Fixed bug where some pages were redirected to incorrect url.
- 2.18.6 Fixed bug where Curio Tags and Descriptions rows were not being highlighted during video playback.
- 2.18.7 Fixed negative timings in some tool windows were shown incorrectly.
- 2.18.8 Fixed long filename in the title bar caused corrupted display.
- 2.18.9 Projects viewer now shows the project creator.
- 2.18.10 Projects and asset packages are now synchronized with changes from other users.
- 2.18.11 Fixed bug in API where IA session failed to create if there were no projects specified in the parameters.
- 2.18.12 Added support for Korean and Japanese code pages for PAC file settings.
- 2.18.13 Errors in SCC files are reported in the Logging Viewer.
- 2.18.14 Highlight invalid times in red in subtitles viewer.
- 2.18.15 Added two-factor authentication for login.
- 2.18.16 Modified the Project Viewer to show both projects and asset packages on 2 separate views.
- 2.18.17 Enable creation of asset packages for a project.
- 2.18.18 Added ability to use indexed searching when finding files in file dialog.
- 2.18.19 When using the API to create an Iris Anywhere session, a parameter can be specified to allow assets to be pulled from S3.

GrayMeta Iris Anywhere / Iris Play

- 2.18.20 Annotations start and end time can be set to the current playing position by right clicking on them.
- 2.18.21 Allow projects to be loaded from a url.
- 2.18.22 Prevent deleting, renaming, creating projects if the user does not have requisite permissions.
- 2.18.23 Segment data in annotations are now synchronized with changes made by other users.
- 2.18.24 Fixed bug where rewind via keyboard or context menu would trigger a step rewind, instead of a normal rewind.
- 2.18.25 Notify user if license is about to expire within 14 days.
- 2.18.26 Removed some warnings and errors that were shown in API documentation.
- 2.18.27 Removed the “File Upload” and “New Folder” buttons in the file open dialog.
- 2.18.28 Fixed bug where shortcut keys were not working.